

PLGM

Keysight DAQ970A/73A Data Acquisition System

USB Firmware Update Procedure for Non-Windows Operating Systems

Release Date: (Table Text)	June 26, 2023
Requirements Category (e.g., operating system):	Microsoft Windows 10, Microsoft Windows 8, Microsoft Windows 7
Requirements Category (e.g., instrument software version):	2.03
Requirements Category (other):	N/A
File Name:	N/A
License:	N/A

Follow below instructions for non-window operating firmware updates:

1. On the DAQ970A firmware update web page under 'Add-On Software/Utilities', select "Firmware Update for Non-Windows Operating Systems" and download the "DAQ970A.zip" file.
2. After the download, extract the files (build.xml and NK.bin) to a folder titled "DAQ970A" on the root directory of the USB drive.

Note: The extracted files are used by DAQ973A as well. The folder must be named as DAQ970A regardless of the model number of the mainframe updated.

3. Attach the USB drive to the instrument front panel and press [Utility] > Admin > Firmware Update to update the firmware.

Note: If Secure mode is enabled, unlock the instrument with the security code before installing firmware.