



Agilent Technologies

Agilent Automated Solder Paste Inspection System Medalist SP 3.1.6.02 Software Release Notes

The Agilent SP 3.1.6.02 software release demonstrates the continued innovation and commitment to improvement in solder joint inspection by Agilent. As part of our continuing software enhancement and support service, Agilent Technologies is releasing the SP 3.1.6.02 software to our valued customers. This is part of Agilent's software update service that provides additional value to the SP50 systems by offering new and improved algorithms and improved overall system stability.

- The revision SP 3.1.6.02 has only been tested with a HP xv4400 running Windows XP Professional.
- The revision SP 3.1.6.02 has not been tested or validated to run on Windows 2000 or any other controller type

Question: Do I need a new license?

Answer: No! If you have software 3.1.1 or 3.1.6 already loaded, you already have a valid license to install 3.1.6.02 full release software. If you need to buy additional licenses, please contact Agilent's Technical Support.

Software Installation Procedure:

To install the new SP 3.1.6.02 revision:

1. Exit out of the SP-GUI application.
2. Backup the current AOIpEngine.exe and spGUI.exe in c:\Program Files\Agilent Technologies\SP Series folder.
3. Unzip the package to a temporary location, example c:\temp folder or desktop.
4. Double click on setup.exe.
5. Select Next.
6. Select Ok.
7. Restart your PC.

Software Reversion Procedure:

To revert to the previously installed version of the SP 3.1.6.01 or earlier software, you will have to:

1. Go to the backup folder that you had created before installing this latest SP 3.1.6.02 software.

2. Right click on AOIpEngine.exe and select Register COM Server.
3. Double click on the spGUI.exe icon to launch the SP-GUI application

Terms & Conditions:

Customer's Software license is transferable upon Agilent's receipt of the name, address and location of transferee and payment of any applicable fees to the extent permissible under local laws. Customer will immediately upon transfer deliver all copies of the Software to the transferee. The transferee must agree in writing to the terms of Customer's license. All license terms will be binding on involuntary transferees, notice of which is hereby given. Customer's license will automatically terminate upon transfer.

Bug Fixes

The "CR" numbers used below, refer to the Change Request numbers in Agilent's software tracking system.

CR33577:	Auto Assign - Bridging Graphics not turned on
Type:	Bug
Problem:	If program by shape ("Auto Assign to Package and Part Number Algorithm"), then turn on bridging for a given Package or Type, the bridging highlighting in Board Graphics is NOT turned on.
Resolution:	Fixed.
