



Agilent 5DX 8.4 Software Release

Software Release Date:	November 2006
5DX System Requirements:	Series 3 & Series 5000
Controller Requirements:	Kayak XU800 or greater
Operating System:	Windows XP ® Professional Service Pack 2
Software Requirements:	8.31

Installation Requirements:

- 384MB of RAM or greater & 500MB of free disk space
- Administrative Rights log on with Administrative privileges.

Installation Instructions for the 5DX & TDW:

1. Perform a full backup of your system to ensure no files are lost.
2. Insert the CD labeled **5DX & TDW System Software 8.4.0. Agilent Part Number: N7210-19532** into the CDROM drive
3. Follow on screen prompts.
4. If you have previously installed 8.3.1, skip to 8.
5. If you have not installed any 8.x software previously, you will be prompted for a **5DX system license file**.
6. Locate the Agilent Software Entitlement Certificate that came with the release. If you are unable to find the certificate, please contact Agilent 5DX support desk.
7. Follow the instructions on the Entitlement certificate to redeem the 5DX system license file and then restart the installation of 8.4.0
8. Once the 5DX reboots, perform an **Automatic Startup**.
9. It is highly recommended to perform a full confirmation & adjustment (C&A) once the 5DX is completed its installation.

More 8.4.0 info at:

www.agilent.com/see/5DX

www.agilent.com/see/support

Worldwide CD-ROM Recycling Centers

www.agilent.com/see/contact_info

Select your county; click GO