

Keysight PX0109A Quick I/V Measurement Software for PXIe Precision SMU

Version 1.0.2538.6810

Release Date:	November 21, 2025
Operating System:	Microsoft Windows 10 Professional(64-bit), Windows 10 (64-bit) Enterprise
Supporting language:	English (US)
.NET Framework:	Microsoft .NET Framework version to 4.8
IO Libraries:	Keysight IO Libraries Suite 2019 or later
PathWave License Manager:	2.4.1 or later
Supported Instruments:	M9601A, M9602A, M9603A, M9614A, M9615A M960x instrument driver 4.7.2568.0 or later
File Name:	PX0109A.1.0.2538.6810.EXE
License:	Requires a License
SHA256 Hash:	38857305b838bd470c4612d4394f6a89f3e43b8e13ca219f665072c3ef895cee

Enhancements

- Updated support for .NET Framework 4.8
- Updated EULA (#43)

Bug Fixes

- Fixed: Installation issue with M960x Driver 4.7.2586.0 (#42)

Version 1.0.2216.6280

Release Date:	April 25, 2022
Operating System:	Microsoft Windows 10 Professional(64-bit), Windows 10 (64-bit) Enterprise
Supporting language:	English (US)
.NET Framework:	Microsoft .NET, Framework 4.7.1
IO Libraries:	Keysight IO Libraries Suite 2019 or later
PathWave License Manager:	2.4.1 or later
Supported Instruments:	M9601A, M9602A, M9603A, M9614A, M9615A
File Name:	QuickIV.1.0.2216.6280.EXE
License:	Requires a License

Enhancements

- Supported: Shorter delay between each channel of the M9614/15A by the Sync Line function. (#39)

Bug Fixes

- Fixed: Out of range errors may occur on second and subsequent executions, regardless of the same settings. (#32)
- Fixed: Improper Power Source settings on M9614/15A. (#33)
- Fixed: Unexpected error “Operation not supported for instrument model M96xxA” may occur if the slot order and device number order of the VISA address do not match. (#36)
- Fixed: CONST may not be enabled after execution with VAR1 settings. (#37)

Version 1.0.2136.3330

Release Date:	September 9, 2021
Operating System:	Microsoft Windows 10 Professional(64-bit), Windows 10 (64-bit) Enterprise
Supporting language:	English (US)
.NET Framework	Microsoft .NET, Framework 4.7.1
IO Libraries	Keysight IO Libraries Suite 2019 or later
PathWave License Manager	2.4.1 or later
Supported Instruments	M9601A, M9602A, M9603A, M9614A, M9615A
File Name:	QuickIV.1.0.2136.3330.EXE
License:	Requires a License

Initial Release