



## **Agilent N6465A eMMC Compliance Test Application Software Release Notes**

---

### **Agilent N6465A eMMC Software Version 01.03**

**Released Date: 4 Apr 2014**

**Minimum Infiniium Oscilloscope Baseline Version: 4.20.0000**

**File Name: SetupInfeMMC01030006.exe**

1. This will be the last version to support Baseline 4.20.

### **Agilent N6465A eMMC Software Version 01.03**

**Released Date: 4 Apr 2014**

**Minimum Infiniium Oscilloscope Baseline Version: 4.10.0000**

**File Name: SetupInfeMMC01030005.exe**

2. Patch to update to clearly separate tODLY and tOH measurement.

### **Agilent N6465A eMMC Software Version 01.03**

**Released Date: 26 Nov 2013**

**Minimum Infiniium Oscilloscope Baseline Version: 4.10.0000**

**File Name: SetupInfeMMC0103.exe**

3. Added logic to additionally search for CMD23 followed by block read or write.
4. With no specification for when data must transition after a read or write command, added an auto increase in memory acquisition to search for a data transition before error that it cannot find a read or write. Previously, would search in a fixed memory for data transitions.

### **Agilent N6465A eMMC Software Version 01.02**

**Released Date: 8 Aug 2013**

**Minimum Infiniium Oscilloscope Baseline Version: 4.10.0000**

**File Name: SetupInfeMMC0102.exe**

5. Updated read/write trigger to use CMD17/18 and CMD 24/25 serial logic.
6. Added a config variable to allow the user to increase or decrease wait time for read and write separation. This is to allow for DUTs that have little control of read/write and may have long times between.

### **Agilent N6465A eMMC Software Version 01.01**

**Released Date: 27 Feb 2013**

**Minimum Infiniium Oscilloscope Baseline Version: 4.10.0000**



## **Agilent Technologies**

**File Name: SetupInfeMMC0101.exe**

7. Fixed UDF enable bug.
8. Fixed screen capture for rise/fall times to show worst case.

**Agilent N6465A eMMC Software Version 01.00**

**Released Date: 11 Jan 2013**

**Minimum Infiniium Oscilloscope Baseline Version: 4.10.0000**

**File Name: SetupInfeMMC0100.exe**

**Initial release.**